



## วิธีการการใช้ Microsoft Outlook 2007 ในการส่งอีเมลผ่าน wide

1. เปิดโปรแกรม "Microsoft Outlook 2007" เลือกรายการ "Tools" | "Account Settings" จากนั้นคลิกเลือก Account ที่ต้องการตั้งค่า outgoing mail ดังรูป



2. หลังจากนั้นคลิกปุ่ม Change... จะปรากฏดังรูป



3. ทำการเลือกที่ Outgoing mail server (SMTP) และใส่ค่าเป็น mail.wide.me ดังรูป

**Change E-mail Account**

**Internet E-mail Settings**  
Each of these settings are required to get your e-mail account working.

**User Information**  
Your Name: widemail  
E-mail Address: widemail@wide.me

**Server Information**  
Account Type: POP3  
Incoming mail server: mail.wide.me  
Outgoing mail server (SMTP): mail.wide.me

**Logon Information**  
User Name: widemail@wide.me  
Password: [REDACTED]  
 Remember password  
 Require logon using Secure Password Authentication (SPA)

**Test Account Settings**  
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)  
Test Account Settings ...

More Settings ...

< Back   Next >   Cancel

#### 4. เลือก More Settings ... ดังรูป

**Change E-mail Account**

**Internet E-mail Settings**  
Each of these settings are required to get your e-mail account working.

**User Information**  
Your Name: widemail  
E-mail Address: widemail@wide.me

**Server Information**  
Account Type: POP3  
Incoming mail server: mail.wide.me  
Outgoing mail server (SMTP): mail.wide.me

**Logon Information**  
User Name: widemail@wide.me  
Password: [REDACTED]  
 Remember password  
 Require logon using Secure Password Authentication (SPA)

**Test Account Settings**  
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)  
Test Account Settings ...

More Settings ...


< Back   Next >   Cancel

#### 5. เมื่อเลือก More Settings แล้วจะปรากฏดังรูปให้ทำตามขั้นตอนดังนี้


1. เลือก Outgoing Server
2. ทำเครื่องหมายที่ My outgoing server (SMTP) requires authentication
3. เลือกที่ Logon using และใส่รหัสผ่านดังนี้

Username: xxxx@wide.me  
Password: xxxxxxxx

4. กด OK



6. ทำการทดสอบการส่ง-รับ Email เพื่อดูว่าสามารถใช้งานได้หรือไม่ดังรูป



7. หากทำการตั้งค่าต่างๆถูกต้องโปรแกรมจะแจ้งดังรูป

